

PRESCRIPTION TREATMENT® brand

GY-KICK®

Crack & Crevice® Pressurized Residual

For Pest Control Operators and Commercial Use Only

KILLS: Ants, Booklice, Boxelder Bugs, Carpenter Ants, Carpenter Bees, Centipedes, Chocolate Moths, Clover Mites, Cluster Flies, Cockroaches, Crickets, Dermestids, Drug Store Beetles, Earwigs, Elmleaf Beetles, Flour Beetles, Grain Weevils, Millipedes, Scorpions, Silverfish, Sowbugs, Spiders, Springtails, Termites*, Ticks, Trogoderma (Cabinet, Khapra, and Warehouse Beetles), Wood Infesting Borers and Beetles, and Wood Wasps.

* Not a substitute for mechanical alteration, soil or foundation treatment.

FOR USE IN AND AROUND: Apartments***, Campgrounds, Food Storage Areas, Homes***, Hospitals*, Hotels, Meat Packing and Food Processing Plants, Motels, Nursing Homes*, Resorts, Restaurants and other Food Handling Establishments, Schools**, Supermarkets, Transportation Equipment (Buses, Boats, Ships, Trains, Trucks), Utilities, Warehouses, and other Commercial and Industrial Buildings.

* Remove patients before using. After treatment, ventilate rooms for 30 minutes before returning patients to rooms.

** Do not apply to classrooms when in use. Do not apply to institutions (including libraries, sport facilities, etc.) in the immediate area when occupants are present.

*** In the home, all food processing surfaces and utensils should be covered during treatment or thoroughly washed before use. Exposed food should be covered or removed.

ACTIVE INGREDIENTS:

Cyfluthrin 0.1%

OTHER INGREDIENTS:

..... 99.9%

EPA Reg. No. 499-470 EPA Est. No. 499-MO-1

KEEP OUT OF REACH OF CHILDREN

CAUTION

See side panel for additional Precautionary Statements.

DIRECTIONS FOR USE

IT IS A VIOLATION OF FEDERAL LAW TO USE THIS PRODUCT IN A MANNER INCONSISTENT WITH ITS LABELING.

HOW TO USE WHITMIRE MICRO-GEN CRACK AND CREVICE® INJECTION SYSTEM

CRACK & CREVICE® TREATMENT: Use TC 198 with the supplied actuator and injection tubes or other Whitmire Micro-Gen equipment. Inject TC 198 into cracks and crevices or void spaces where insects may be harboring, living and breeding. Place injector tip into cracks, crevices, holes and other small openings. Release approximately one second of product. For light infestations, move injector tip along cracks while treating at the rate of three linear feet per second. For heavy infestations, move injector tip along at one linear foot per second. For closed voids, calculate the void's cubic area and treat at the rate of one to five seconds per three cubic feet. Several holes may be required in long-running voids.

SPOT TREATMENT: Use TC 198 with the supplied actuator and injection tubes or other Whitmire Micro-Gen equipment. Hold container upright while spraying. Direct nozzle approximately 12 inches from surface to be treated. Apply directly on insects in these locations when possible.

INDOOR TREATMENTS

CRAWLING INSECTS - Cockroaches, Dermestids, Scorpions, Spiders, Earwigs, Crickets, Sowbugs, Millipedes, Centipedes:

Apply as a Crack and Crevice® treatment using the prescribed dosage into cracks, crevices and void spaces where insects may be harboring. These may include, but are not limited to, openings around pipes and sinks, under refrigerators, behind baseboards, washing machines, stoves, cabinets, sewers, floor drains and meter boxes. Spot treatment may also be made to areas including, but not limited to, storage areas; closets; around water pipes, doors and windows; around refrigerators, cabinets, sinks, stoves and other equipment; shelves, drawers and similar areas.

Ticks: Apply as a Crack and Crevice® treatment or spot treatment into infested and egg laying sites near pet resting areas including, but not limited to, cracks and crevices of baseboards and around door and window frames.

Booklice & Silverfish: Apply as a Crack and Crevice® treatment into cracks and crevices of baseboards, door frames, bookcases and other harborage sites. Spot treatment may also be made to areas including, but not limited to, storage areas; closets; around water pipes, doors and windows; around refrigerators, cabinets, sinks, stoves and other equipment; shelves, drawers and similar areas.

Ants: Apply as a Crack and Crevice® treatment into cracks, crevices and voids where ants may be trav-

eling and/or harboring, including, but not limited to, around doors, window frames, wall voids and other structural cracks and crevices. Spot treatment may also be made to areas including, but not limited to, storage areas; closets; around water pipes, doors and windows; around refrigerators, cabinets, sinks, stoves and other equipment; shelves, drawers and similar areas.

Grain Weevils, Flour Beetles, Chocolate Moths, Drugstore Beetles, Trogodermas (in exposed adult and larval stages) and hibernating stages of Boxelder Bugs, Elmleaf Beetles, Cluster Flies and Clover Mites: Apply as a Crack and Crevice® treatment into cracks, crevices and/or voids where these insects may be harboring or hibernating. Infested areas may include, but are not limited to, cracks and crevices in cabinets and pantries, wall voids, around window and door frames, under siding and in machinery. Spot treatment may also be made to areas including, but not limited to, storage areas; closets; around water pipes, doors and windows; around refrigerators, cabinets, sinks, stoves and other equipment; shelves, drawers and similar areas.

APPLICATIONS IN FOOD HANDLING ESTABLISHMENTS

Food handling establishments are places other than private residences in which food is held, processed, prepared or served.



WHITMIRE MICRO-GEN
RESEARCH LABORATORIES, INC.

NOTE: This specimen label is for informational purposes only. All uses may not be approved in all states. See labeling which accompanied product for Directions for Use or call 800-777-8570 for more information.